



# Advance MAM Platform



# MAM Account

MAM accounts is the best tool for managing pool of clients in a unique way. It was developed specifically for professional money managers and hedge funds managers

**Account type in manager's app is called**

- Signal Manager (For Master)
- Signal Investor (For investor)

## Main features

1. 7 allocation methods
2. Activation / Deactivation of investors without closing positions
3. Trader can use several master accounts for managing his pool of investors
4. Fees for all investors can be set up separately
5. All fees are paid automatically
6. MAM-Master accounts are not shown in leader board.
7. Money manager can use several master accounts for managing his pool of investors with different allocation methods, risk ratios and activated/deactivated investors
8. All investors in MAM are in read-only mode. Investors cannot trade by their own
9. Investors can see their opened positions on their MT4 accounts.
10. Deposits and withdrawals don't affect master account's equity as accounts are separate.

## Allocation methods for MAM:

1. Proportionally by Balance
2. Proportionally by Equity
3. Proportionally by Balance x Ratio
4. Proportionally by Equity x Ratio
5. Proportionally by Free margin
6. Fix lot allocation
7. Ratio Multiplier

## Formulas for allocation methods:

- 1. Proportionally by Balance**  
Position of investor = Master position x (Investor's balance / Master's Balance)
- 2. Proportionally by Equity**  
Position of investor = Master position x (Investor's Equity / Master's Equity)
- 3. Proportionally by Balance x Ratio**  
Position of investor = Master position x (Investor's balance / Master's Balance) x Ratio
- 4. Proportionally by Equity x Ratio**  
Position of investor = Master position x (Investor's Equity / Master's Equity) x Ratio
- 5. Proportionally by Free margin**  
Position of investor = Master position x (Investor's free margin / Master's free margin)
- 6. Fixed lot allocation**  
Position of investor = fixed lot (ratio)  
Position of investor is opened in the direction of master trade
- 7. Ratio Multiplier (sometimes called lot allocation)**  
Position of investor = Master position x Ratio

## Where money manager can manage his investors

Money manager manages his investors on "My investors" page in My accounts section.

What money manager can do here:

1. activate / deactivate investors
2. change ratio
3. set min lot setting
4. change allocation method
5. see list of investors
6. see investors' orders

# Min lot setting

Sometimes investor has a small deposit or money manager trade very small lot and projected size of position that should be opened on investment account is lower than minimal lot allowed on a server

## For example

Master position x (Investor's Equity / Master's Equity) x Risk Ratio < 0.01 lot for EURUSD). For opening position even in such situations, he can activate option "always open min lot". You can find a checkbox "open min lot". See the screenshot.

The screenshot displays a trading platform interface with a dark theme. At the top, there is a dropdown menu for 'Master account name' with the value '90277'. Below this is a navigation bar with tabs: 'My Investors', 'Trading report', 'Orders', 'Deposit', 'Withdraw', 'Settings', and 'Statistics'. The main content area is divided into two sections: 'Investors' and 'Orders'. The 'Investors' section shows a table with columns: 'Login', 'Active', 'Ratio', 'Positions', 'Balance', 'Equity', 'Currency', 'Margin', 'Free margin', and 'HWM'. Two investors are listed: 90279 and 90278. The 'Orders' section shows a table with columns: 'Order', 'Inv. login', 'Type', 'Symbol', 'Lot', 'Open price', 'Current price', 'Open time', and 'Profit USD'. Two orders are listed: 9060660 and 9060661. At the bottom, there is an 'Account status' section with fields for 'Balance', 'Equity', 'Free margin', and 'Margin lvl'. A red circle highlights the 'Always open min. lot' checkbox in the 'Investors' section, and a red arrow points to it.

Investors	2 investors									
★	Login	Active	Ratio	Positions	Balance	Equity	Currency	Margin	Free margin	HWM
☆	90279	✓	1	1	22,000.00	21,910.80	USD	1,955.66	19,955.14	0
☆	90278	✓	1	1	10,000.00	9,959.95	USD	878.05	9,081.90	0

  

Orders	2 orders							
Order	Inv. login	Type	Symbol	Lot	Open price	Current price	Open time	Profit USD
9060660	90279	Buy ↑	GBPJPY#	1.47	145.391	145.34	-	-68.62
9060661	90278	Buy ↑	GBPJPY#	0.66	145.391	145.34	-	-30.81

  

Account status	Balance	Equity	Free margin	Margin lvl
	\$15,000.00	\$14,943.90	\$13,613.63	1,123.37%

## How activation / deactivation works

Master account name  
90277

My Investors | Trading report | Orders | Deposit | Withdraw | Settings | Statistics

Investors | 2 investors | Always open min. lot | Allocation method: Proportional by Equity\*Ratio

★	Login	Active	Ratio	Positions	Balance	Equity	Currency	Margin	Free margin	HWM
☆	90279	<input checked="" type="checkbox"/>	1	1	22,000.00	21,910.80	USD	1,955.66	19,955.14	0
☆	90278	<input type="checkbox"/>	1	1	10,000.00	9,959.95	USD	878.05	9,081.90	0

Orders | 1 orders

Order	Inv. login	Type	Symbol	Lot	Open price	Current price	Open time	Profit USD
9060661	90278	Buy	GBPJPY#	0.66	145.391	145.34	-	-30.81

Account status

Balance \$15,000.00 | Equity \$14,943.90 | Free margin \$13,613.63 | Margin lvl 1,123.37%

On the screen above you can see 2 investors. One of them activated and the other one - not.

If money manager deactivates investor - he will not receive a new position that will be opened after deactivation.

BUT all opened positions before deactivation will remain active on investment account after deactivation and will be closed respectively when money manager will close master position on his master account.